
WLAN Android to Windows profiler

User Guide



Features

- Import profiles
- Export profiles (backup)
- Port your wifi networks from your android device
- Auto 'networks' folder detect

Supports

- WPA / WPA2 networks

Requirements

- .Net Framework 3.5 and above

Importing

For import, select Folder, optional select the user you want to assign the profiles (by default is all users in the computer), and last select the Wireless adapter you want.

Exporting

For export, select Folder and Wireless adapter.

Converting

For converting wifi networks to Windows profiles, select the file "wpa_supplicant.conf" that I assume you pulled from your phone and just select if you want to 'just convert' which means that the program will only convert them and export them in the folder "networks", else if you want to import them too select the 'Convert and Import'.

The file must be in form below:

```
network={
    ssid="Wifi network 1"
    psk="2145986749864273"
    key mgmt=WPA-PSK
    priority=49
}
network={
    ssid="Wifi network 2"
    psk="4c17esomepassword"
    key mgmt=WPA-PSK
    priority=52
}
network={
    ssid="Wifi network 3"
    psk="password123456"
    key_mgmt=WPA-PSK
    priority=427
}
```

Debugging mode

If you want to see in more detailed what is going on or if encounter a error check on the arrow button on the bottom of the window to trigger the Log view.

